Steps to activate IE Mode (Internet Explorer Mode) in Microsoft Edge

Microsoft declared it will discontinue support for and retire Internet Explorer 11 on June 15, 2022. However, some repair manuals and publications still depend on IE11 features to operate effectively. Fortunately, Microsoft Edge web browser offers a solution to enable this functionality.

The information below provides the specifics on how to activate IE Mode.

Step 1) Open the Microsoft Edge browser

New tab	Ctrl+T
New window	Ctrl+N
New InPrivate window	Ctrl+Shift+N
Zoom	— 100% + ⤢
Favorites	Ctrl+Shift+O
Downloads	Ctrl+J
Extensions	
Collections	Ctrl+Shift+Y
Print	Ctrl+P
Web capture	Ctrl+Shift+S
Share	
Find on page	Ctrl+F
Read aloud	Ctrl+Shift+U
More tools	>
Settings	
Help and feedback	>
Close Microsoft Edge	

Step 2) Access and click the **[Settings]** menu via the three dots icon in the top-right corner.

Settings

Q Search settings

- Profiles
- Privacy, search, and services
- Appearance
- On startup
- New tab page
- Share, copy, and paste
- Cookies and site permissions
- Default browser
- Downloads
- Family safety
- Languages

Step 3) Select [**Default Browser**] **from the**

Default browser

Make Microsoft Edge your default browser   Make default

Internet Explorer compatibility

Let Internet Explorer open sites in Microsoft Edge ⑦   Incompatible sites only (Recommended) ⌄
When browsing in Internet Explorer you can choose to automatically open sites in Microsoft Edge

Allow sites to be reloaded in Internet Explorer mode ⑦   ◯
When browsing in Edge, if a site requires Internet Explorer for compatibility, you can choose to reload it in Internet Explorer mode

4. Enable the toggle switch for "**Allow sites to be reloaded in Internet Explorer mode**"

Step 5) Click the "**Restart**" button to re-launch Microsoft Edge

Step 6) Browse to **www.toyotamanuals.com.au or www.lexusmanuals.com.au**

Step 7) Click the 3 dots menu up in the top right and select **More tools** and then select **"Reload in Internet Explorer Mode"**